

EFI Metrix Release Notes

Version 2020.1.0.575

Copyright © 2004 - 2020 by Electronics for Imaging, Inc. All Rights Reserved.

EFI Metrix 2020.1 | EFI Metrix Release Notes

August 2020 / EFI Metrix 2020.1

Document Version 1

This publication is protected by copyright, and all rights are reserved. No part of it may be reproduced or transmitted in any form or by any means for any purpose without express prior written consent from Electronics for Imaging, Inc. Information in this document is subject to change without notice and does not represent a commitment on the part of Electronics for Imaging, Inc.

Patents

This product may be covered by one or more of the following U.S. Patents: 4,716,978, 4,828,056, 4,917,488, 4,941,038, 5,109,241, 5,170,182, 5,212,546, 5,260,878, 5,276,490, 5,278,599, 5,335,040, 5,343,311, 5,398,107, 5,424,754, 5,442,429, 5,459,560, 5,467,446, 5,506,946, 5,517,334, 5,537,516, 5,543,940, 5,553,200, 5,563,689, 5,565,960, 5,583,623, 5,596,416, 5,615,314, 5,619,624, 5,625,712, 5,640,228, 5,666,436, 5,745,657, 5,760,913, 5,799,232, 5,818,645, 5,835,788, 5,859,711, 5,867,179, 5,940,186, 5,959,867, 5,970,174, 5,982,937, 5,995,724, 6,002,795, 6,025,922, 6,035,103, 6,041,200, 6,065,041, 6,112,665, 6,116,707, 6,122,407, 6,134,018, 6,141,120, 6,166,821, 6,173,286, 6,185,335, 6,201,614, 6,215,562, 6,219,155, 6,219,659, 6,222,641, 6,224,048, 6,225,974, 6,226,419, 6,238,105, 6,239,895, 6,256,108, 6,269,190, 6,271,937, 6,278,901, 6,279,009, 6,289,122, 6,292,270, 6,299,063, 6,310,697, 6,321,133, 6,327,047, 6,327,050, 6,327,052, 6,330,071, 6,330,363, 6,331,899, 6,340,975, 6,341,017, 6,341,018, 6,341,307, 6,347,256, 6,348,978, 6,356,359, 6,366,918, 6,369,895, 6,381,036, 6,400,443, 6,429,949, 6,449,393, 6,476,927, 6,490,696, 6,501,565, 6,519,053, 6,539,323, 6,543,871, 6,546,364, 6,549,294, 6,549,300, 6,550,991, 6,552,815, 6,559,958, 6,572,293, 6,590,676, 6,606,165, 6,633,396, 6,636,326, 6,643,317, 6,647,149, 6,657,741, 6,662,199, 6,678,068, 6,707,563, 6,741,262, 6,748,471, 6,753,845, 6,757,436, 6,757,440, 6,778,700, 6,781,596, 6,816,276, 6,825,943, 6,832,865, 6,836,342, RE33,973, RE36,947, D341,131, D406,117, D416,550, D417,864, D419,185, D426,206, D439,851, D444,793.

Trademarks

The APPS logo, AutoCal, Auto-Count, Balance, Best, the Best logo, BESTColor, BioVu, BioWare, ColorPASS, Colorproof, ColorWise, Command WorkStation, CopyNet, Cretachrom, Cretaprint, the Cretaprint logo, Cretaprinter, Cretaroller, DockNet, Digital StoreFront, DirectSmile, DocBuilder, DocBuilder Pro, DocStream, DSFdesign Studio, Dynamic Wedge, EDOX, EFI, the EFI logo, Electronics For Imaging, Entrac, EPCount, EPPhoto, EPRegister, EPStatus, Estimate, ExpressPay, Fabrivu, Fast-4, Fiery, the Fiery logo, Fiery Driven, the Fiery Driven logo, Fiery JobFlow, Fiery JobMaster, Fiery Link, Fiery Prints, the Fiery Prints logo, Fiery Spark, FreeForm, Hagen, Inktensity, Inkware, Jetrion, the Jetrion logo, LapNet, Logic, MiniNet, Monarch, MicroPress, OneFlow, Pace, PhotoXposure, PressVu, Printcafe, PrinterSite, PrintFlow, PrintMe, the PrintMe logo, PrintSmith, PrintSmith Site, Printstream, Print to Win, Prograph, PSI, PSI Flexo, Radius, Rastek, the Rastek logo, Remoteproof, RIPChips, RIP-While-Print, Screenproof, SendMe, Sincrolor, Splash, Spot-On, TrackNet, UltraPress, UltraTex, UltraVu, UV Series 50, VisualCal, VUTEk, the VUTEk logo, and WebTools are trademarks of Electronics For Imaging, Inc. and/or its wholly owned subsidiaries in the U.S. and/or certain other countries.

All other terms and product names may be trademarks or registered trademarks of their respective owners, and are hereby acknowledged.

Table of Contents

Welcome to Metrix 2020.1	4
Contact Information	4
System Requirements	5
Licensing	
New Features	7
Known Issues for the Metrix 2020.1 Release	7
Key Fixes	. Error! Bookmark not defined.

Welcome to Metrix 2020.1

EFI Metrix is an industry-leading job planning engine that transforms big data into actionable data in the most proven end-to-end integrated solution with a holistic view into manufacturing. With over 1,200 Metrix users in 25 countries and 12 years of continuous, aggressive development, Metrix is recognized as the de facto industry standard for dynamic, intelligent production planning, and automated imposition. Metrix 2020.1 introduces new features and enhancements and addresses issues found in previous releases.

Contact Information

EFI Support

Web Site:	communities.efi.com
US Phone:	1.855.EFI.4HLP (1.855.334.4457)
UK Phone:	+44 (0) 800.783.2737
EU Phone:	+49.2102.745.4500
E-Mail:	metrix.support@efi.com

Metrix Support hours are 8AM CET to 5pm ET Monday – Friday. You may contact support at the above numbers or via our customer portal at communities.efi.com.

Note For problems involving infrastructure (e.g., computers, networks, operating systems, backup software, printers, third-party software, etc.), contact the appropriate vendor. EFI cannot support these types of issues.

EFI Professional Services

US Phone:	(651) 365-5321
US Fax:	(651) 365-5334
F-Mail:	ProfessionalServicesOperations@efi.com

Notes EFI Professional Services can help you perform EFI software installations, upgrades, and updates. This group can also help you implement, customize, and optimize your EFI software plus offer a range of training options.

System Requirements

Please ensure your system is running one of the supported operating systems listed below before beginning the installation process.

Metrix 2020.1 system requirements:

- Metrix 2020.1 requires 64-bit systems. It will not run on 32-bit systems.
- Metrix now supports Mac OS X 10.15 (Catalina)

Microsoft has ended support for Windows 7 and Windows Server 2008 effective January 14, 2020, so Metrix 2020.1 will no longer support these platforms. We recommend you upgrade your system to Metrix current minimum system requirements.

For more information on the installation process, please see the EFI Metrix 2020.1 Installation Guide.

Windows Minimum System Requirements for Metrix 2020.1

Windows Minimum System Requirements for Metrix 2020.1		
Processor	Intel compatible	
Processor Speed	1 GHz minimum	
Windows Operating System	Microsoft Windows 10.x (64-bit)	
	Microsoft Windows 8.x (64-bit)	
	 Microsoft Windows Server 2019 (64-bit) 	
	 Microsoft Windows Server 2016 (64-bit) 	
	 Microsoft Windows Server 2012 R2 (64-bit) 	
	 Microsoft SQL Server 2014 SP3 and SP4 (64-bit) 	
	 Microsoft SQL Server 2016, 2017, and 2019 	
	Note Metrix no longer supports Microsoft Windows 7.x or Windows Server 2008.	
Memory	Metrix Client – 2 GB RAM	
	Metrix Data Server – 2 GB RAM	
	 Automation Server Pro – 16 GB RAM (Minimum) to 4 GB RAM per CPU Core (64 GB RAM Maximum) 	
	 Automation Server Enterprise – 64 GB RAM (Minimum) to 4 GB RAM per CPU Core (256 GB RAM Maximum) 	
	eFlow License Manager – 256 MB RAM	
Monitor Resolution	• 1024 x 768 or higher	
Network (multi-user)	 Static IP address for the Data Server, eFlow License Manager, and Automation Server. Automation Server runs as a service and needs a local administration account. 	
	Notes If you use the Content Previews module, the minimum RAM requirement for Metrix is 6 GB with 8 GB or more recommended.	
	The Content Previews module is processor intensive, so a fast multi-core processor is recommended. If PDF content is being accessed across a LAN, gigabit network speeds are recommended when accessing large content files.	

Mac OS X Minimum System Requirements for Metrix 2020.1

Processor Speed 1 GHz minimum Macintosh Operating System OS X 10.15 (Catalina) (see Note below) OS X 10.14 (Mojave) OS X 10.13 (High Sierra) OS X 10.12 (Sierra) OS X 10.11.x (El Capitan) OS X 10.9.x (Mavericks)	
 Macintosh Operating System OS X 10.15 (Catalina) (see Note below) OS X 10.14 (Mojave) OS X 10.13 (High Sierra) OS X 10.12 (Sierra) OS X 10.11.x (El Capitan) OS X 10.10.x (Yosemite) 	
 OS X 10.14 (Mojave) OS X 10.13 (High Sierra) OS X 10.12 (Sierra) OS X 10.11.x (El Capitan) OS X 10.10.x (Yosemite) 	
 OS X 10.13 (High Sierra) OS X 10.12 (Sierra) OS X 10.11.x (El Capitan) OS X 10.10.x (Yosemite) 	
 OS X 10.12 (Sierra) OS X 10.11.x (El Capitan) OS X 10.10.x (Yosemite) 	
 OS X 10.11.x (El Capitan) OS X 10.10.x (Yosemite) 	
• OS X 10.10.x (Yosemite)	
OS X 10 9 x (Mayericks)	
5 00 / 10.0.x (Marchold)	
was eFlow LIM is unable to run on Mac OS X 10.15 (Catalina) be Mac OS X 10.15 (Catalina) does not support 32-bit application eFlow LIM will run on Mac OS X 10.12 (Sierra) through OS X 10.14 (Mojave).	ons.
Note Metrix requires Java 11. Metrix installs and uses this version internally, regardless of the Java version that is installed on computer.	
Memory • Metrix Client – 2 GB RAM	
Metrix Data Server – 2 GB RAM	
eFlow License Manager – 256 MB RAM	
Monitor Resolution • 1024 x 768 or higher	
Network (multi-user) • Static IP address for the Data Server and eFlow License Management	jer.
Notes If you use the Content Previews module, the minimum R requirement for Metrix is 6 GB with 8 GB or more recommended.	.AM
The Content Previews module is processor intensive, so multi-core processor is recommended. If PDF content is accessed across a LAN, gigabit network speeds are recommended when accessing large content files.	

Licensing

Upgrade your eFlow License Manager to the latest version to ensure optimum performance and security. The installers can be found on https://www.efi.com/marketing/productivity-software/downloads/metrix-installers/.

Notes eFlow LIM is not supported on Mac OSX 10.15 (Catalina).

If you are installing eFlow LIM on any version of Mac OS X, see the *EFI Metrix 2020.1 Installation Guide* for instructions and important information.

Key Fixes

Default Content Folder location

Changes to the Default Content Folder are saved. (Issue Reference: 14423)

Changing Customer Product Property

Changing the Customer Product Property is correctly applied and does not automatically revert to the previous setting. (Issue Reference: 14459)

Known Issues for the Metrix 2020.1 Release

- Users upgrading from Metrix 2016.1 or earlier will be required to back up their database, install 2019.2, and then upgrade the database before they can install 2020.1 and upgrade the database again. (Issue Reference: 14185)
- Metrix will not save the default printer in the Export window. (Issue Reference: 8441, 13310)
- The Auto Expand Trims option does not work with Auto Layout. (Issue Reference: 12858)
- Japanese fonts print as indecipherable text when there are multiple PDFs in a project that contain fonts with the same name but different glyphs. (Issue Reference: 13452)
- For die-cut products, Page to Bleed Gap is not correctly applied when Auto Page to Bleed Gap is set to False. (Issue Reference: 13482)
- Unable to scroll beyond the right or top edges of a sheet when a layout is magnified. (Issue Reference:
- The Allowed Bleed Intrusions setting for die-cutting tools is non-functional at this time. (Issue Reference: 13208)
- Die-cutting tools and standards created in 2018.1 may show errors when opened in 2020.1. In 2018.1, if the multi-up file used to create a die-cutting tool had horizontal and/or vertical offsets defined, Metrix ignored them, but in 2020.1 the offsets are applied. This may result in misalignment of the die-cutting tool on the sheet and/or errors in standards and projects that use the die-cutting tool (for example, "Sheet must be large enough for Die-cut Tool").

Workaround: Edit the die-cutting tool and change the Anchor Horizontal Offset, Anchor Vertical Offset, Minimum Sheet Width, and Minimum Sheet Height values. (Issue Reference: 14296)